Issues with COLTT

4/15/2010

(1) COLTT 1.08.4

Running COFE (COCO 1.16) with COLTT 1.08.4 enabled and Aspen CAPEOPEN 1.0 (Aspen Properties 24.0) or Aspen COMThermo 1.0 (V7.2):

Flowsheet configuration:	×
Property packs Reaction packs Compounds Properties Phase Info Material types Flo	wsheet Options
Thermo-systems and prop 🎇 Select Thermo Pack or Property Pa 💶 💌 💳	
⊕-1 Aspen COMThermo (CAPE-OPEN 1.0)	Add
🕀 🏤 Aspen COMThermo (CAPE-OPEN 1.1)	Remove
🗄 🦓 Aspen Properties 21.0	Edit
Aspen Properties 22.0	
Aspen Properties 23.0	Rename
 	Info
E - May CapeOpen.CThermoSystem	
🖶 🚋 Multiflash CO 1.1 Package	
😥 🌆 Multiflash CD Package	
🕀 🌇 Multiflash Property Package Manager	
🕀 🦓 Multiflash Thermo System	
OATS Property Package Manager (CAPE-OP-	
⊕∰g OATS Thermo System (CAPE-OPEN 1.0) ⊕∰g TEA (CAPE-OPEN 1.0)	
About OK Cancel	
Description:	

Clicked on OK, it crashed (COFE closed). From debugger you would see:

File	Edi	t Vie	w	Proj	ect	De	ebug	Tools	Test	Window	Hel											
ì	+	- 2	76	lé		Ж	Þ	B 9	- (²¹	• @ •	4				-					-	🥙 rvp)
▶	00		a	⇔	*1	≶ ⊒	Ç⊒	≧ <u>≣</u> He>	- 😪	📬 - 📮												
Pro	cess:	[3472]	CO	FE.e:	ke			 Thread: 	[317	6] Main Thr	ead		- 1	۲	Sta	ick Fram	: COL	oggers:	5T.dll!	100661	5b()	-
Di	sasse	mbly)																			
Add	lress:	10066	15b																			
	1006	6137	C6	45	FC	04		mov		byte	otr	ebp	-4],	4								
	1006	613B	8B	4D	08			mov		ecx,d	Jord	ptr	[eb	p+8]								
	1006	613E	83	Cl	50			add		ecx,5		-										
	1006	6141	E8	E5	во	F9	FF	call		10001												
	1006	6146	89	85	ЗC	FE	FF	FF mov		dwor	1 pt	: [e	bp-1	C4h]	,eax							
	1006	614C	8B	F4				mov		esi,e			-									
	1006	614E	8B	8D	зc	FE	FF	FF mov		ecx,	- iwor	l pt	r [e]	bp-1	[4h]							
	1006	6154	51					push		ecx		-		-								
	1006	6155	8B	95	зc	FE	FF	FF mov		edx,	lwor	l pt	r [e]	bp-1	[4h]							
>	1006	615B	8B	02				mov		eax,d		-		-								
	1006	615D	8B	48	24			mov		ecx,d		-			a]							
	1006	6160	FF	Dl				call		ecx		-										
	1006	6162	ЗВ	F4				cmp		esi,e	sp											
	1006	6164	E8	6B	BD	05	00	call		10001	3D4											
	1006	6169	89	85	38	FE	FF	FF mov		dwor	1 pt	: [e	bp-1	C8h]	,eax							
	1006	616F	8B	95	38	FE	FF	FF mov		edx,	lwor	l pt	r [e!	bp-1	[8h]							
	1006	6175	89	55	EO			mov		dword		-		-								
all S	itack																					
N	ame																					
0	OLoaa	ersST.	d !1(0066	15b()																
						ir.	andi	or missina.	no svr	nbols loade	d for	OLor	aders ^c	T.dll1								
-		xe!004					anap	or moonly)	10 571		2101		,90,90	. rang								
		xe!004		~																		
		xe!005		~~																		
		xe!003		~ ~																		
		xe!006		~~																		
		xe!006																				
		xe!006		~~~																		

If running with COLTT 1.08.4 off, it worked fine.